Sega NAOMI

The Sega NAOMI (stands for “New Arcade Operation Machine Idea”) is a arcade developed by Sega. It was released in 1998. Designed to be the successor to the Model 3, it uses similar architecture to that of the Dreamcast. Because of this, emulation of NAOMI games is usually best done with a Dreamcast emulator (modifications have already been made to allow for this in Flycast, for instance). Features arcade games like Crazy Taxi, Dead or Alive 2 and Samba de Amigo.

Although “NAOMI” can refer to multiple different types of boards released by Sega during this time period, Batocera specifically refers to just the original NAOMI board released in 1998 when mentioning “NAOMI” (at least for now).

Due to the similarity between NAOMI and the Dreamcast, most games were also ported to the Dreamcast, and a few even getting ported to other consoles of the generation. It may be easier to attempt to emulate those than their arcade counterparts.

For those interested in the hardware aspect, here's a cool article about it on Sega Retro.

This system scrapes metadata for the “naomi” and “arcade” groups and loads the `naomi` set from the currently selected theme, if available.



Quick reference

- **Accepted ROM formats:** `.lst`, `.bin`, `.dat`, `.zip`, `.7z`
- **Folder:** `/userdata/roms/naomi`

Emulators
libretro: Flycast
Flycast
Demul

BIOS

The BIOS is optional but I dunno you probably want to include it anyway.

MD5 checksum	Share file path	Description
eb4099aeb42ef089cfe94f8fe95e51f6	bios/naomi.zip	NAOMI MAME BIOS

Some games have optional extra BIOS files that can be used, but they aren't required to run them.

MD5 checksum	Share file path	Description
	hod2bios.zip	The House of the Dead 2 MAME BIOS
	f355dlx.zip	Ferrari F355 Challenge Deluxe MAME BIOS
	f355bios.zip	Ferrari F355 Challenge Twin/Deluxe MAME BIOS
	airlbios.zip	Airline Pilots Deluxe MAME BIOS

ROMs

Place your Sega NAOMI ROMs in `/userdata/roms/naomi`.

User-friendly compatibility list for Flycast.

If you're willing to search through code, here's the list of all the expected ROM hashes.

Some NAOMI boards use just ZIP ROMs to run, but most others use a ZIP in addition to an image (or CHD) file. In order to use ROMs that come with a image, the image must be placed in a subfolder with the same name as the game's ZIP file with the MAME ID as its filename. For example:

```
roms/
└─ naomi/
   ├─ ikaruga/
   │  └─ gdl-0010.chd
   └─ ikaruga.zip
```

Emulators

RetroArch

RetroArch (formerly SSNES), is a ubiquitous frontend that can run multiple “cores”, which are essentially the emulators themselves. The most common cores use the libretro API, so that's why cores run in RetroArch in Batocera are referred to as “libretro: (core name)”. RetroArch aims to unify the feature set of all libretro cores and offer a universal, familiar interface independent of platform.

RetroArch configuration

RetroArch offers a **Quick Menu** accessed by pressing [HOTKEY] +  which can be used to alter

various things like RetroArch and core options, and controller mapping. Most RetroArch related settings can be altered from Batocera's EmulationStation.

Standardized features available to all libretro cores: `naomi.videomode`, `naomi.ratio`, `naomi.shaderset`, `naomi.smooth`, `naomi.integerscale`, `naomi.bezel`, `naomi.bezel_stretch`, `naomi.hud`, `naomi.bezel.tattoo`, `naomi.bezel.tattoo_corner`, `naomi.bezel.tattoo_file`, `naomi.bezel.resize_tattoo`, `naomi.ai_service_enabled`, `naomi.ai_target_lang`, `naomi.ai_service_url`, `naomi.ai_service_pause`, `naomi.integerscale`, `naomi.runahead`, `naomi.secondinstance`, `naomi.video_frame_delay_auto`, `naomi.vrr_runloop_enable`, `naomi.video_threaded`

ES setting name `batocera.conf_key`	**Description ⇒ ES option `key_value`**
Settings that apply to all cores of this emulator	
GRAPHICS BACKEND `naomi.gfxbackend`	Choose your graphics rendering ⇒ OpenGL `opengl`, Vulkan `vulkan`.
AUDIO LATENCY `naomi.audio_latency`	Audio latency in milliseconds, turn it up if you hear crackles ⇒ 256 256, 192 192, 128 128, 64 64, 32 32, 16 16, 8 8.
ALLOW ROTATION `naomi.video_allow_rotate`	Allow cores to set rotation. ⇒ On `true`, Off `false`.
CONTROLLER TO LIGHTGUN `naomi.lightgun_map`	Map controller inputs to lightgun inputs ⇒ On `true`, Off `false`.

libretro: Flycast

A fork of a fork of a fork... this is an identical version of standalone Flycast but inside of a libretro core. Makes use of RetroArch's features.

libretro: Flycast configuration

ES setting name `batocera.conf_key`	**Description ⇒ ES option `key_value`**
Settings that apply to all systems this core supports	
SYNCHRONOUS RENDERING `global.reicast_synchronous_rendering`	When threaded rendering is on (on by default), waits for the GPU to finish rendering the frame before dropping the current one. This can avoid certain emulation issues (flashing screens, glitchy video). Significant performance cost. Recommended “Off” for most games as they don't experience issues (or you have a weak machine), “On” if the game has these particular issues. ⇒ Off `disabled`, On `enabled`.

ES setting name `batocera.conf_key`	Description ⇒ ES option `key_value`
RENDERING RESOLUTION **`global.reicast_internal_resolution`**	Enhancement. Increases the rendering resolution. Makes 3D objects clearer. Significant performance cost. Use `640×480` for native. Absurdly high values can degrade image quality (pixels beginning to shimmer). ⇒ `640×480` `640×480`, `800×600` `800×600`, `960×720` `960×720`, `1024×768` `1024×768`, `1280×960` `1280×960`, `1440×1080` `1440×1080`, `1600×1200` `1600×1200`, `1920×1440` `1920×1440`, `2560×1920` `2560×1920`, `3200×2400` `3200×2400`, `3840×2880` `3840×2880`, `4480×3360` `4480×3360`, `5120×3840` `5120×3840`, `5760×4320` `5760×4320`, `6400×4800` `6400×4800`, `7040×5280` `7040×5280`, `7680×5760` `7680×5760`.
TEXTURE MIP-MAPPING (BLUR) **`global.reicast_mipmapping`**	Enables mip-mapping to smooth out textures on distant 3D objects based on distance and angle. Dreamcast games natively utilized mipmapping to get extra performance out of the hardware, but the extra bluriness from doing this is more apparent on modern, higher fidelity screens. Has a minimal performance cost. `enabled` should be used in conjunction with anisotropic filtering to mitigate bluriness. Some users may prefer the 'sharpness' of `disabled` better. ⇒ Off `disabled`, On `enabled`.
ANISOTROPIC FILTERING **`global.reicast_anisotropic_filtering`**	Enables anisotropic filtering to enhance perspective textures. Dramatically improves the clarity of textures on distant 3D objects when mip-mapping is turned on, especially at higher internal resolutions. Test Drive: Le Mans is the only Dreamcast game that natively utilizes this. Has a small performance cost. Generally safe to use 16x when mip-mapping is also enabled, leave on “Off” otherwise. ⇒ Off `False`, 2x 2, 4x 4, 8x 8, 16x 16.
TEXTURE UPSCALING (XBRZ) **`global.reicast_texupscale`**	Enhancement. Applies xBRZ upscaling to textures to improve their clarity. Improvements are subjective. ⇒ Off `False`, 2x 2x, 4x 4x, 6x 6x.

ES setting name `batocera.conf_key`	**Description ⇒ ES option `key_value`**
RENDER TO TEXTURE UPSCALING `global.reicast_render_to_texture_upscaling`	Enhancement. Some 3D games would capture the screen output and render it as a 2D texture (eg. pause menu in Crazy Taxi and Dead or Alive), being unaffected by `reicast_internal_resolution`. This setting multiplies the resolution of that capture. Example here. “Off” for native, “4x” for close-to 1080p rendering (only useful if also upscaling the internal resolution). ⇒ Off 1x, 2x 2x, 3x 3x, 4x 4x, 8x 8x.
FRAMESKIP `global.reicast_frame_skipping`	Skip frames to improve performance, at the cost of choppy motion. Higher values can cause motion sickness if used for extended periods. Should only be turned up on weak hardware and if immune to motion sickness. ⇒ Off `disabled`, 1 1, 2 2, 3 3, 4 4, 5 5, 6 6.
FORCE WINDOWS CE MODE `global.reicast_force_wince`	Some Dreamcast games (marked “Powered by Microsoft Windows CE” on the box, eg. Sega Rally 2) utilized the MMU Windows Compact Edition API on the Dreamcast to run. Batocera should automatically detect this but in case it doesn't you can manually override it here. Significant performance cost. ⇒ Off `disabled`, On `enabled`.
WIDESCREEN CHEAT (PRIORITY) `global.reicast_widescreen_cheats`	Enhancement. Flycast has a database of cheats that can enable widescreen support in certain games, rendering them in anamorphic widescreen without changing the internal resolution. Some games also natively support widescreen in their in-game options. A 16/9 ratio must be used and bezels must be disabled. ⇒ Off `disabled`, On `enabled`.
WIDESCREEN HACK `global.reicast_widescreen_hack`	Enhancement. Changes the internal resolution to a widescreen ratio (eg. 640×480 becomes 853×480). Somewhat glitchy. Some games also natively support widescreen in their in-game options. A 16/9 ratio must be used and bezels must be disabled. ⇒ Off `disabled`, On `enabled`.
CONTROLLER 1 TYPE `global.controller1_dc`	Chooses the controller plugged into port 1. ⇒ Gamepad 1, Keyboard 3, Mouse 2, Light Gun 4.
CONTROLLER 2 TYPE `global.controller2_dc`	Same as above for port 2. ⇒ Gamepad 1, Keyboard 3, Mouse 2, Light Gun 4.

ES setting name `batocera.conf_key`	**Description ⇒ ES option `key_value`**
CONTROLLER 3 TYPE `global.controller3_dc`	Same as above for port 3. ⇒ Gamepad 1, Keyboard 3, Mouse 2, Light Gun 4.
CONTROLLER 4 TYPE `global.controller4_dc`	Same as above for port 4. ⇒ Gamepad 1, Keyboard 3, Mouse 2, Light Gun 4.
Settings specific to atomiswave	
SCREEN ORIENTATION `atomiswave.screen_rotation_atomiswave`	Rotate screen for some arcade games ⇒ Horizontal `horizontal`, Vertical `vertical`.
Settings specific to naomi	
SCREEN ORIENTATION `naomi.screen_rotation_naomi`	Rotate screen for some arcade games ⇒ Horizontal `horizontal`, Vertical `vertical`.

All other settings can be configured from RetroArch's **Quick Menu** → **Options** (`[HOTKEY]` + ).

Flycast

Flycast is a fork of Reicast (which itself is a fork of nullDC). A highly compatible and accurate standalone Dreamcast emulator.

Flycast can also be used to run NAOMI arcade games due to being nearly identical hardware. Not all NAOMI games are compatible yet but most of them are.

Flycast configuration

Standardized features available to all cores of this emulator: `dreamcast.videomode`, `dreamcast.videomode`, `dreamcast.bezel`, `dreamcast.bezel_stretch`, `dreamcast.hud`, `dreamcast.bezel.tattoo`, `dreamcast.bezel.tattoo_corner`, `dreamcast.bezel.tattoo_file`, `dreamcast.bezel.resize_tattoo`

ES setting name `batocera.conf_key`	**Description ⇒ ES option `key_value`**
Settings that apply to all cores of this emulator	
SCREEN RATIO `naomi.flycast_ratio`	Choose which screen ratio you want to use. ⇒ Default `False`, Widescreen `True`.
RENDER RESOLUTION `naomi.flycast_render_resolution`	Choose which internal rendering resolution you want to use. ⇒ 320×240 (Half) `240`, 640×480 (Native) `480`, 960×720 (x1.5) `720`, 1280×960 (x2) `960`, 1600×1200 (x2.5) `1200`, 1920×1440 (x3) `1440`, 2560×1920 (x4) `1920`, 2880×2160 (x4.5) `2160`.
GRAPHICS API `naomi.flycast_renderer`	Choose your graphics renderer. ⇒ OpenGL (Default) `0`, Vulkan `4`.

ES setting name `batocera.conf_key`	Description ⇒ ES option `key_value`
ROTATE SCREEN 90 DEGREES `naomi.flycast_rotate`	Rotate the screen by 90 degrees. ⇒ Normal `False`, Rotate `True`.

All other configuration must be done via the `flycast-config` in the Applications folder (`[F1]` on the systems screen).

Demul

From their FAQ:

> Demul is Sega's multi-system game console and automaton emulator, originally intended solely to emulate the Sega Dreamcast game console. Currently, the emulator also supports emulation of Sega Dreamcast-based slot machines: Naomi, Naomi 2 and Atomiswave . Support for Sega Model 3, Sega Hikaru, Sega Saturn is under development .

Demul configuration

Standardized features available to all cores of this emulator: `naomi.videomode`, `naomi.bezel`, `naomi.bezel_stretch`, `naomi.hud`, `naomi.bezel.tattoo`, `naomi.bezel.tattoo_corner`, `naomi.bezel.tattoo_file`, `naomi.bezel.resize_tattoo`

ES setting name `batocera.conf_key`	Description ⇒ ES option `key_value`
Settings that apply to all cores of this emulator	
GAME ASPECT RATIO `global.demulRatio`	⇒ Stretch `0`, 4:3 (Default) 1, 16:9 2.
VSYNC `global.demulVSync`	Fix screen tearing. ⇒ Off `0`, On 1.

Controls

How does this even work?

Here are the default Sega Naomi's controls shown on a Batocera Retropad:

Troubleshooting

Further troubleshooting

For further troubleshooting, refer to the generic support pages.

From:
https://wiki.batocera.org/ - **Batocera.linux - Wiki**

Permanent link:
https://wiki.batocera.org/systems:naomi?rev=1650446936

Last update: **2022/04/20 09:28**