2024/04/25 17:46 1/3 Display Troubleshooting

Display issues, where xrandr is your friend

This tutorial is useful if you have display issues, for instance if you need to rotate your screen, or anything else.

For example, I have a 4k UHD TV, Batocera will display the highest display resolution available on my screen, but 4k isn't good for emulation: it's lagging. So, I need to force a smaller resolution.

First of all, you need to connect on your Batocera through SSH, let's use Putty for this! You can find a "How to" by following this link.

Okay, now you're connected on your Batocera, let's begin.

```
# cp /etc/X11/xinit/xinitrc ~/.xinitrc
# export DISPLAY=:0.0
# xrandr
```

Search this section on xrandr:

```
Screen 0: minimum 8 x 8, current 1366 x 768, maximum 32767 x 32767

LVDS1 connected primary 1366x768+0+0 (normal left inverted right x axis y axis) 290mm x 160mm

1366x768 60.03*+ 40.03

1024x768 60.00

1024x576 60.00

960x540 60.00

800x600 60.32 56.25

864x486 60.00

640x480 59.94
```

Here's the available display resolution for your screen. This is an example with an old 4/3 screen, but this is the same principle for other screens.

The current resolution is marked with a "*". I want to change it, so let's use vi - or any other text editor you are familiar with:

```
# vi ~/.xinitrc
```

You'll see a section with:

Just uncomment the corresponding line. In my case, I want to force the 64×480 mode, so I just remove the first # character to:

```
# change the resolution

xrandr -s 640x480

# change the resolution and the Hz

...
```

Let's save and quit ([Esc]:wq for vi).

Actually, your Batocera's display isn't in full screen yet. You must see it only partially, so you have to enter the following commands into your SSH session:

```
# exec emulationstation --windowed
```

Then restart Emulstation:

```
# /etc/init.d/S31emulationstation stop
# /etc/init.d/S31emulationstation start
```

Batocera should be in full screen with the right resolution.

!!\ BUT /! if you reboot the Batocera system, you'll have to do this again, the resolution is forced just for this boot, next boot, resolution will be reset to the highest available again.

We need to force it for every boot.

As you can see at the beginning of this tutorial, we copied the xinitrc file to a temporary folder. We need to erase the current xinitrc file with our modified version. It is the same as the first code block, but reversed:

```
# cp ~/.xinitrc /etc/X11/xinit/xinitrc
# batocera-save-overlay
```

Now, reboot your Batocera system, the display resolution should be good.

Also, xrandr can do screen rotation: very useful for old vertical screen arcade machines!

Hope this was easy for all.

https://wiki.batocera.org/ Printed on 2024/04/25 17:46

2024/04/25 17:46 3/3 Display Troubleshooting

From:

https://wiki.batocera.org/ - Batocera.linux - Wiki

Permanent link:

https://wiki.batocera.org/display_issues?rev=1580240312

Last update: 2020/01/28 20:38

