

# udev Rules

[udev](#) stands for *userspace /dev* and is a device manager for the Linux kernel. The `/dev` path is ordinarily where device information is accessed from, *udev rules* allow you to alter this information in a predictable and permanent manner. For example, what drivers to use/blacklist for a specific device being plugged in.

udev rules are checked when:

1. Booting up, all udev rules are parsed and a rules database is built in memory
2. When an event happens, it checks its rule database and performs the appropriate actions.

In a nutshell, udev rules do always have two major parts:

- **Matches** ("If the condition(s) matches"...). The operator for matches are `==` and `!=`
- **Actions** (... "then do this!"). The operator for actions is: `=`

## udev rules in Batocera

Batocera supports booting up and event udev rules like with any ordinary operating system. These can be manipulated in the usual `/etc/udev/rules.d/` directory. However, changes cannot be permanently stored there due to Batocera's filesystem ([overlays](#) can be used, but are forgotten between upgrades).

But if you only need event udev rules, then the `/userdata/system/udev/rules.d/` path can be used instead. The path must be initially created manually.

For example, if you wanted to enable the [Bluetooth passthrough udev rule of Dolphin](#) for your own Bluetooth dongle (list of compatible adapters **for Dolphin, not necessarily Batocera** is [further down that page](#)), you would use this file:

### 52-dolphin.rules

```
SUBSYSTEM=="usb", ATTRS{idVendor}=="YOURVID",  
ATTRS{idProduct}=="YOURPID", TAG+="uaccess"
```

Replace the values `YOURVID` and `YOURPID` according to your specific device found in the list mentioned above. Then save it and copy it to `/userdata/system/udev/rules.d/52-dolphin.rules` and reboot Batocera.



If the udev rule does not function in this path, then it is a booting up udev rule and must use the aforementioned `/etc/udev/rules.d/` directory.





If you need something activated earlier in the boot process or something more intimate to the system, you can instead use [boot scripts](#).

## Deeper explanation of udev rules

As an example, let's take the udev rule `52-dolphin.rules` from above to dive a little deeper into udev rules:

`SUBSYSTEM`, `ATTRS{idVendor}` and `ATTRS{idProduct}` are all variables that do all have a `==` between them and their assigned values. This means they are all *matches* (conditions). On the other hand, the last variable `TAG` does have a `+=`, which adds itself to any other `TAG` action being executed on this specific event (e.g. by an additional udev rule matching the same event).

This udev rule can be read as follows:

*If the detected device is a USB device with the vendor ID 'YOURVID' and the product ID 'YOURPID', then, in addition to any other TAG action on this specific event, tag the device with 'uaccess' (which provides access to the /dev/ file for the logged in user (in case of Batocera, mostly **root** user)).*

## Viewing and editing pre-existing udev rules

Once Batocera has booted you can view the existing udev rules for your system in `/etc/udev/rules.d/`. You can do this from the file manager ([F1] on the system list) and going up one level, or [via SSH](#). You cannot access this location from the network share, as it is outside of the userdata partition.

## Troubleshooting

If you find that your udev rule isn't working after reboot for any reason, you can alternatively try putting your `*.rules` file directly into `/etc/udev/rules.d/` and running `batocera-save-overlay` afterward. This will call it slightly earlier in the boot process. Remember: Everything saved to the boot partition via `batocera-save-overlay` will get lost after updating Batocera to a new version.

## Transform a keyboard to a pad

- Unordered List Item connect as ssh
- identify your keyboard : run `evtest`. (in my case, this is the event3)

```
# evtest
No device specified, trying to scan all of /dev/input/event*
Available devices:
/dev/input/event0:  Lid Switch
/dev/input/event1:  Sleep Button
/dev/input/event2:  Power Button
```

```
/dev/input/event3: AT Translated Set 2 keyboard
/dev/input/event4: Video Bus
/dev/input/event5: Video Bus
/dev/input/event6: HDA Intel PCH Headphone
/dev/input/event7: HDA Intel HDMI HDMI/DP,pcm=3
/dev/input/event8: HDA Intel HDMI HDMI/DP,pcm=7
/dev/input/event9: HDA Intel HDMI HDMI/DP,pcm=8
/dev/input/event10: FocalTechPS/2 FocalTech Touchpad
/dev/input/event11: Asus WMI hotkeys
/dev/input/event12: 8Bitdo 8BitDo N30 Pro 2
/dev/input/event13: USB2.0 HD UVC WebCam: USB2.0 HD
Select the device event number [0-13]:
```

- create an udev rule to set this event as a joystick.

```
echo 'SUBSYSTEM=="input", ATTRS{name}=="AT Translated Set 2 keyboard",
MODE="0666", ENV{ID_INPUT_JOYSTICK}="1", ENV{ID_INPUT_KEYBOARD}="0" ' >
/etc/udev/rules.d/99-custom.rules
```

- reread rules

```
udevadm control --reload-rules && udevadm trigger
```

- check the flag is present

```
udevadm info -q all -n /dev/input/event3
```

From:

<https://wiki.batocera.org/> - **Batocera.linux - Wiki**

Permanent link:

[https://wiki.batocera.org/udev\\_rules?rev=1647755935](https://wiki.batocera.org/udev_rules?rev=1647755935)

Last update: **2022/03/20 05:58**

