

Easy & Advanced Arcade

Introduction

This page is dedicated to beginners for helping them to easily play arcade games on Batocera.

Arcade has long been the most complicated of emulations due to its very own nature: arcade machines don't all use the same hardware, so they all have to be emulated independently. Imagine you want to play 5 different arcade games, you could have to use 5 different hardware emulators, whereas playing 5 different SNES games will only need the one and only SNES emulator.

That's why MAME has been invented: MAME is kind of a meta-emulator, it brings all the different emulated hardwares of arcade machines into one system, making it simpler for the user to play arcade games without any knowledge of the underlying arcade machine on which the games are launched. It is no small feat and this is why MAME is so complicated to use.

General MAME principles

There are only two main principles to know to get a good grasp of how to use MAME on your recalbox: Romsets and BIOS/driver files

What is a romset

A romset is a set of all the different game roms emulated by a MAME version.

A romset contains parent game roms which are roms corresponding to the 'main' version of a game and clone game roms which are 'alternative' versions of a parent rom. As you can guess, in most cases we will discard all clone roms and only use the main (or parent) ones.

Most of the code used to make those game roms playable is included in the MAME emulator. Sadly this means that there is a strong and close relationship between a MAME version and the game roms versions : When MAME releases a new version, game roms may need to be updated to fit to the new emulator version.

To keep it simple: if you use a certain MAME emulator, say version 0.78, you also have to get your hands on and use the 0.78 version of the romset.

Some games from another romset may work with your version but **the only way to be sure that the most games are working is to use only a MAME version in conjunction with the romset of the same version.**

For recent versions (such as the one used by FBNeo, see below) there are less and less modifications of game roms, so it is sometime possible to use an older set and still have most of the games playable, but once again : **the only way to be sure that the most games are working is to use only a MAME version in conjunction with the romset of the same version.**

Types of romsets

In addition to having a version number, romsets can be found in three different flavours :

- **Non-merged:** All ROMs can be used standalone because each zip contains all the files needed to run that game, including any files from 'parent ROMs'. This is the recommended format.
- **Split:** Some ROMs that are considered clones, translations, or bootlegs also require a "parent ROM" to run. The parent ROM is often the first or most common variant of a game. In some cases the parent is not the most popular or best working version of the game, however. For example, in a Split set pacman.zip (a clone), will not work without puckman.zip (its parent).
- **Merged:** Clones are merged into the parent ROM zip, meaning that more than one game is stored per file. Merged ROM sets are not recommended.

For Batocera the recommended type of romset is the non-merged version

BIOS / Drivers

Some of the game roms from a romset may additionally need BIOS files, the most well known case being neogeo games.

Let's use that as an example : If you want to use neogeo games, you'll have to copy the needed bios/driver file (in that case _neogeo.zip_) in the same folder as the game.

That's all !

Of course if you use different subfolders for your games (genre subfolders or hardware type subfolders for instance) you'll have to copy the BIOS file in every folder containing games which may need it.

Given that they are pretty small files, it's better to copy them all in each of your subfolders.

Where do I find the BIOS files do you say ? Well it's very simple : they are included in your romset ! So if a game doesn't launch and goes back right away to the Emulation Station screen, just try to find the relevant BIOS file and copy it in the game folder.

Arcade Emulation on Batocera

Default emulators

There are several arcade emulators included in Batocera, but just using the default one will be enough for running the majority of games on your Raspberry Pi. Those two systems are :

- Mame 2003
 - mame/romset version : 0.78
 - roms folder : mame

- FBNeo
 - FBNeo is kind of an alternative version of MAME (emulating less arcade machines), but it follows exactly the same principles which I just explained
 - FBNeo romset version : FBNeo 0.2.97.44 this corresponds to MAME 0.187 more or less but not entirely, once again it's better to use the FBNeo 0.2.97.44 romset
 - roms folder : fbneo

Now some games will only work on Batocera with Mame and some others only with FBNeo.

For further details on all the different arcade emulators in Batocera, see the list in Advanced section

Use arcade emulation on Batocera !

First download the full romsets for both emulators : romset 0.78 for Mame and latest romset 0.2.97.44 for FBNeo.

You may rather download each game one by one because full romsets are quite large, but it's usually very difficult to find individual roms and to be sure that they are in the right version. Full Romsets are the only way to avoid headaches !

The romset files must be in zip format, 7z is not supported and in the next section, when you are told to copy your bios or roms, you must copy the zip files without decompressing them, otherwise, it will not work.

You're now just a few steps away from playing some awesome arcade games on Batocera.

Copy your Bios/drivers

First we are going to copy BIOS/drivers files from our romsets. Contrary to other systems, these files must not be copied into the bios folder but inside the dedicated roms folder.

- Get these BIOS/Drivers files from your MAME 0.78 romset and copy them into the mame roms folder: acpsx.zip, cpzn1.zip, cpzn2.zip, cvs.zip, decocass.zip, konamigx.zip, megaplay.zip, megatech.zip, neogeo.zip, nss.zip, pgm.zip, playch10.zip, skns.zip, stvbios.zip, taitofx1.zip, tps.zip
- Copy these BIOS/Drivers files from your FBNeo (0.2.97.44) romset and copy them into the fbneo roms folder, I only needed three of them: neogeo.zip, pgm.zip and skns.zip

Copy games

- Copy your mame roms from the complete 0.78 romset to the mame roms folders
- Copy your FBNeo roms from the complete FBNeo 0.2.97.44 romset (or any other close to that) into the fbneo rom folders
- PLAY ! (or not)

You can also use this list to see if a given mame works on a given emulator or not : [BestArcade](#) and

determine more easily which emulator is the best for the game you want to play.

Further Tricks

- If you want to hide your BIOS files in Emulation Station, edit their metadata with the select menu, add a tag `<hidden>true</hidden>` to your game
- Remember, if you want to use subfolders in your roms folders, just make a copy of BIOS/drivers files into every subfolder and then move your game into the subfolder

Advanced Arcade Emulation on Batocera

ClrMamePro

In order to verify the roms you have are in the right romset version, you can use some softwares to check your them, like ClrMamePpro or RomCenter

CHD

Some more recent arcade games can use extra files called CHD, a copy of the harddrive the game was using at the same time. To use CHD for a game, just place the CHD folder alongside your rom zip, at the same level.

All the arcade emulators on Batocera

See [MAME](#) for now

NeoGeo system

The Neogeo system is not an emulator itself, but uses FBNeo emulator in the background. You can use this system to visually separate the NeoGeo games from the other arcade games, they will appear as a dedicated system in Emulation Station It uses off course the same romset than the FBNeo emulator.

From:

<https://wiki.batocera.org/> - **Batocera.linux** - Wiki

Permanent link:

<https://wiki.batocera.org/arcade?rev=1589129607>

Last update: **2020/05/10 18:53**

