This article needs some TLC. Read at your own risk.

Doom3

Previously known as Boom3, dhewm3 is a Doom 3 source port which brings many fixes and support for various hardware. It is based on Doom 3 game released in 2004.

This system scrapes metadata for the “pc” group(s) and loads the doom3 set from the currently selected theme, if available.

Prior to v41, the system's name was boom3. It is grouped with the “ports” group of systems.



Quick reference

- **Folder:** roms/doom3/
- **BIOS required?** None.

Emulators	Accepted ROM formats	ROM path	Notes
libretro: boom3	.boom3	roms/doom3	Prior to v41, path is /userdata/roms/boom3
dhewm3	.d3	roms/doom3	Starting v41

BIOS

No Boom3 emulator in Batocera needs a BIOS file to run.

ROMs

Place your Doom3 ROMs in `/userdata/roms/doom3`.

Example file structure:

```
└── roms/
    └── doom3/
        ├── base/
        │   ├── base.boom3 (for boom3 core)
        │   ├── pak000.pk4
        │   ├── pak001.pk4
        │   ├── pak002.pk4
        │   ├── pak003.pk4
        │   ├── pak004.pk4
        │   ├── pak005.pk4
        │   ├── pak006.pk4
        │   ├── pak007.pk4
        │   └── pak008.pk4
        ├── d3xp/
        │   ├── d3xp.boom3 (for boom3 core)
        │   ├── pak000.pk4
        │   └── pak001.pk4
        ├── Doom 3.d3 (standalone emulator)
        └── Doom 3 - Resurrection of Evil.d3 (standalone emulator)
```

The `Doom 3.d3` file should contain the path to the base game. - i.e. `base/pak000.pk4`

Similarly `Doom 3 - Resurrection of Evil.d3` should be - `d3xp/pak000.pk4`

Emulators

RetroArch

RetroArch has its own page.

libretro: boom3

libretro: dhewm3

Controls

Here are the default Boom3's controls shown on a Batocera RetroPad:

Troubleshooting

Further troubleshooting

For further troubleshooting, refer to the generic support pages.

From:
https://wiki.batocera.org/ - **Batocera.linux - Wiki**

Permanent link:
https://wiki.batocera.org/systems:doom3?rev=1728831488

Last update: **2024/10/13 14:58**